

WorkInSync Single Sign On - Azure AD

(Applicable for workinsync.io based client urls)

Document Control	
Document Name	WorkInSync Single Sign On
Version No	1.2
Classification	Internal
Last Modified Date	01/02/2022

Version Control				
Ver No.	Author	Approved by	Approved Date	Description
1.0	Manvi	Nitin Awasthi	15/12/2021	First version
1.1	Nitin Awasthi	Akash M	01/02/2022	Title update
1.2	Aditya Dutt	Ujjwal	27/06/2023	Mobile SSO section



WorkInSync application supports SSO SAML 2.0 and can integrate with any Identity Provider (called IDP also known as Asserting Party) that uses this protocol for communication.

SSO integration requires a set of items to be exchanged by both parties, namely Service Provider (SP aka Relying Party) & Identity Provider (IDP) for set-up.

In this case, WorkInSync is the Service provider or relying party in this case.

For any typical SSO integration, the customer needs to provide following information to WorkInSync:

1. Issuer ID or Entity ID
2. Redirect URL for Login
3. Redirect URL for Logout
4. X509 Certificate
5. Which 3rd party tool the customer is using like ADFS, Pingdom Federation,, Shibboleth, etc. (Good to know)

As an alternative, If customer IDP is ADFS or Azure active Directory, the customer needs to share only the "FederationMetadata.xml" file. Customers may also provide a link to download this file. In case of the Azure active directory, it can be downloaded from the "SAML Signin Certificate" section on your Azure portal.**

Note: The customer must also provide the username type, which they use for SSO. WorkInSync currently supports only one username type:

i.e. Email ID


(Other username type e.g. employee ID are not supported as of now)

WorkInSync will provide following information to the Customer

1. Relay URL - Customer site URL (e.g <https://<clientname>.workinsync.io>)
2. Target URL - Endpoint to receive SAML response from IDP.
3. Redirect URL - Landing page URL after successful authentication. Same as Relay URL.
4. Relay State -


OR

If customer IDP supports uploading of SP metadata, only a metadata xml file would be provided which is sufficient.



****Steps to download the Federation Metadata file from Azure Active Directory**

1. On the Azure portal, Go to Azure Active Directory
2. Select Enterprise applications in the left hand menu
3. In the list of applications select the application you have configured to give SSO access to workinsync
4. Then select 'Single sign on' to see the 'SAML Signing Certificate' section as shown below.
5. Download the file from the 'Download' button next to 'Federation Metadata xml' or copy and share the link corresponding to 'App Federation Metadata Url'



The screenshot shows the Azure portal interface for configuring a SAML-based sign-on. The left sidebar contains navigation options: Overview, Deployment Plan, Manage (Properties, Owners, Roles and administrators (Preview), Users and groups), Single sign-on (selected), Provisioning, Application proxy, Self-service, Security (Conditional Access, Permissions, Token encryption). The main content area is titled 'wis-sami-test | SAML-based Sign-on' and includes a sub-header 'Enterprise Application'. Below this, there are four numbered steps: 1. Upload metadata file, 2. Change single sign-on mode, 3. Test this application, and 4. Got feedback? The main configuration area is divided into three sections: 2. User Attributes & Claims, 3. SAML Signing Certificate, and 4. Set up wis-sami-test. The 'User Attributes & Claims' section shows a table with attributes and their corresponding claims. The 'SAML Signing Certificate' section shows the status as 'Active' and provides download links for the certificate in Base64, Raw, and Federation Metadata XML formats. The 'Set up wis-sami-test' section is currently empty.

Attribute	Claim
givenname	user.givenname
surname	user.surname
emailaddress	user.mail
name	user.userprincipalname
Unique User Identifier	user.userprincipalname

Property	Value
Status	Active
Thumbprint	4C324B0B52314140740B20D00C...
Expiration	9/3/2024, 10:31:15 AM
Notification Email	vrmiranj@moveinsync.onmicrosoft.com
App Federation Metadata Url	https://login.microsoftonline.com/3cc0b6c0-c00c-...
Certificate (Base64)	Download
Certificate (Raw)	Download
Federation Metadata XML	Download

Note: The customer must also provide the username type, which they use for SSO. WorkInSync currently supports only one username type:

i.e. Email ID

(Other username type e.g. employee ID are not supported as of now)

WorkInSync will provide following information to the Customer

1. Relay URL - Customer site URL (e.g <https://<clientname>.workinsync.io>)
2. Target URL - Endpoint to receive SAML response from IDP.
3. Redirect URL - Landing page URL after successful authentication. Same as Relay URL.
4. Relay State -

OR


If customer IDP supports uploading of SP metadata, as in the case of ADFS or Azure Active Directory, only a metadata xml file would be provided which is sufficient. See the next section on [how to upload SP Metadata to Azure active Directory to setup SSO](#).

Configuring WorkInSync app on your Azure Active Directory for SSO


Prerequisite

Please reach out to KDV to get the metadata file to be shared with the customer.


1. Login to your Azure Portal (<https://portal.azure.com>) with administrator credentials
2. Go to 'Enterprise Applications' either from 'frequently used apps' list of front page or via global search on top



3. Click on 'New Application' and then 'Create your own application'




4. Give a name you can recollect later if needed e.g. 'WorkinSync SSO' . In the radio options let 'Integrate any other application you don't find in the gallery (Non-gallery)' option remain selected.






5. Select 'Setup single signon'



6. Select 'SAML' as the single sign on method





7. Select 'Upload metadata file' option, and upload the metadata file provided to you by WorkInSync. This file would be typically named as 'workinsync-prod-sp.xml' or similar

WorkInSync SSO Demo | SAML-based Sign-on

Enterprise Application

Overview | Deployment Plan | Manage | Properties | Owners | Roles and administrators (Preview) | Users and groups | Single sign-on | Provisioning | Application proxy | Self-service | Security | Conditional Access | Permissions | Token encryption

Set up Single Sign-On with SAML

Read the [configuration guide](#) for help integrating WorkInSync SSO Demo.

1 Basic SAML Configuration

Identifier (Entity ID) Required
Reply URL (Assertion Consumer Service URL) Required
Sign on URL Optional
Relay State Optional
Logout URL Optional

2 User Attributes & Claims

givenname user.givenname
surname user.surname
emailaddress user.mail
name user.userprincipalname
Unique User Identifier user.userprincipalname

3 SAML Signing Certificate

WorkInSync SSO Demo | SAML-based Sign-on

Enterprise Application

Overview | Deployment Plan | Manage | Properties | Owners | Roles and administrators (Preview) | Users and groups | Single sign-on | Provisioning | Application proxy | Self-service | Security | Conditional Access | Permissions | Token encryption

Set up Single Sign-On with SAML

Read the [configuration guide](#) for help integrating WorkInSync SSO Demo.

1 Basic SAML Configuration

Identifier (Entity ID) Required
Reply URL (Assertion Consumer Service URL) Required
Sign on URL Optional
Relay State Optional
Logout URL Optional

2 User Attributes & Claims

givenname user.givenname
surname user.surname
emailaddress user.mail
name user.userprincipalname
Unique User Identifier user.userprincipalname

3 SAML Signing Certificate


Upload metadata file.

Values for the fields below are provided by WorkInSync SSO Demo. You may either enter those values manually, or upload a pre-configured SAML metadata file if provided by WorkInSync SSO Demo.

workinsync-prod-sp.xml

Add Cancel

8. Once uploaded most of the fields on the 'Basic SAML Configuration' dialog that pops up should be pre-populated.
Make sure the reply URL and relay state fields are filled. The relay state should be your tenantID in WorkinSync.
Save and close the dialog.



9. You are done with the configuration. Check the '[Download federation metadata](#)' section to see how to download the federation data to be shared with WorkinSync.

Whitelist -

Specific URLs need to be whitelisted in the client's network to allow smooth operations -

- <http://code.jquery.com/>